

# Structure on the Project Page

If a project is [enabled for Structure](#), you will see a new Structure icon on the side navigation bar. Clicking this will open the Structure widget on the Project Page.

The screenshot shows the Structure widget interface. Red arrows point to various components: 'Structure name' points to the 'Kanbans' dropdown; 'Automatic filter' points to the 'project = "TIS"' filter; 'Structure tab' points to the 'TIS-6' tab; 'Project issues missing from structure' points to the 'Current Project Issues' section; and 'Options' points to the gear icon in the top right corner. The main panel displays a list of project issues with columns for Key, Summary, and Progress.

Key	Summary	Progress
TIS-4	Next Generation version of SeeSpaceEZ travel platform	
TIS-3	Add support for teams larger than 20 people - Not sure	
TIS-6	Make working with our space travel partners easier - M	
TIS-20	Engage Saturn Shuttle Lines for group tours - Our	
TIS-23	Engage JetShuttle SpaceWays for short distance s	
TIS-25	Engage Jupiter Express for outer solar system trav	

This is a fully-functional Structure widget and has the same functionality you can find on the [Structure Board](#), with the following exceptions:

## Scope

The current project defines the scope of the displayed data:

- An automatic project filter is added to the primary panel, hiding all issues from other projects. This is a non-removable transformation.
- Project issues will be displayed in the secondary panel.



If you'd like to see the full structure without the project filter, click the *Open* link in the Structure widget's footer.

## Layout

When you open the Structure tab, the Single Grid layout is selected automatically. The panel displays the most recently viewed structure or the default structure for the current project (as defined in the Options dialog). You can quickly switch to another structure by clicking the structure name and selecting the desired structure.

## Project Page Options

You can make the widget open with the structure that is defined as a default structure for this specific project.

To do this, click the options gear button in the top right corner and select the **Auto-switch** option. The changes are saved to the server and applied immediately.

The screenshot shows the Structure Settings dialog box. It has a title bar 'Structure Settings' and a checkbox labeled 'Auto-switch to default structure: Manually Built Structure'. Below the checkbox are two buttons: 'Change default structure' and 'Close'. The background shows the Structure widget with the 'Manually Built Structure' tab selected.

If you are the Project Administrator, the options dialog will also show the link to a page where you can change the default structure for your project.



The default value for this option can be configured by the JIRA Administrator on the [Structure Defaults](#) page.

## Perspectives are Unavailable

It is not possible to [share a perspective](#) from the project page.